UrJtag Installation Instructions

Common Commands to use Urjtag after Installation

Connect the Krypton board to your PC and Power it on using slide switch

Open Terminal and type: sudo rmmod ftdi_sio (only Ubuntu 18.04, every time you connect/Power On the Board) and press enter

Open Terminal and type: sudo jtag (ubuntu) and press enter

Run jtag.exe (windows)

Type the command: cable ft2232 vid=0x0403 pid=0x6010 and press enter

Type the command: **detect** and press enter

Type the command: svf <path to file>/filename.svf progress and press enter

**avoid giving "spacebar" in file/folder name, instead use "_" or "-"

**(\) for Windows

**run all the commands everytime you program the HW, no shortcut

Installation of UrJtag on Ubuntu 16.04

**Pendrive also has Ubuntu 16.04 but UrJtag is already installed there, no need to install

Download the folder: urjtag_ubuntu_16.zip from Teams/General/Files/Software_Tutorial_Instructions/

Extract/Unzip the file: urjtag_ubuntu_16.zip
Move to the directory/folder: urjtag_ubuntu_16/

Right click and Open in Terminal

Type the command: **chmod** +**x urjtag.sh** and press enter Type the command: **sudo** ./**urjtag.sh** and press enter

Installation of UrJtag on Ubuntu 18.04

Download the folder: urjtag_ubuntu_18.zip from Teams/General/Files/Software_Tutorial_Instructions/

Extract/Unzip the file: urjtag_ubuntu_18.zip
Move to the directory/folder: urjtag_ubuntu_18/

Right click and Open in Terminal

Type the command: **chmod** +**x dependency.sh** and press enter Type the command: **sudo** ./**dependency.sh** and press enter

Extract/Uncompress the file: urjtag-2019.12.tar.xz Move to the directory/folder: urjtag-2019.12/

Right click and Open in Terminal

Type the command: ./configure and press enter

Type the command: ./configure --disable-dependency-tracking and press enter

Type the command: ./configure and press enter

Type the command: make and press enter

Type the command: sudo make install and press enter

Move to the directory/folder: urjtag_ubuntu_18/

Right click and Open in Terminal

Type the command: **chmod** +**x urjtag.sh** and press enter Type the command: **sudo** ./**urjtag.sh** and press enter

Installation of UrJtag on Windows

Method 1(Portable Version)

Download the folder: urjtag_windows.zip from Teams/General/Files/Software_Tutorial_Instructions/

Extraxt/Unzip the file: urjtag_windows.zip
Move to the directory/folder: urjtag_windows/


Run the file: jtag.exe (right click and run as administrator if normal mode does not work)

Method 2 (Installation Version)

Follow the Instructions given in the video "WindowsUrJtag.mp4" available at Teams/General/Files/Software_Tutorial_Instructions/
Compressed file "altera.zip" is available at Teams/General/Files/Software_Tutorial_Instructions/


Steps to Install Device Driver

FIRST: Connect the Krypton board to your PC and Power On, you will see notification "USB Device not recognized"







SECOND: Open "Device Manager"




THIRD: Drop down "USB Serial Bus Controller", Select "Unknown USB Device", Right click and then click on "Update driver"



FOURTH: Select "Search Automatically for Updated Driver Software"



FIFTH: Remove the Krypton USB Cable and reconnect it, If yellow sign disappears, you are good to go, else follow next step.



SIXTH: Drop down "USB Serial Bus Controller", Select "Unknown USB Device", Right click and then click on "Uninstall device", confirm and click on "OK/Uninstall". Remove the Krypton USB Cable and reconnect it, If yellow sign disappears, you are good to go.

